

Role LB - haproxy Configuration (Debian/Win2019)

Configuration Changes

For **redundant** installations, the haproxy configuration must be maintained on both nodes identically.

Location of Configuration File

The configuration file is located in:

/etc/haproxy/haproxy.cfg

Must Change

The following items must be changed:

Peers Replicates Section

The peer name "localproxy" must be changed to the host name of the proxy server (the short hostname).

This will otherwise cause a warning in the log, and the stick tables will not reload correctly when the server is reloaded.

```
peers replicates
    peer localproxy 127.0.0.1:1024
```

Configure Redirects

The configuration file allows redirects from the following URLs to the correct login page:

- Root requests directly to the load balancer are redirected to **/CarrierPortal/login/RESELLER/CLIENT**
- Requests to **/mini** are redirected to the mini client login page **/CarrierPortal/mclogin/RESELLER/CLIENT**

Modify the redirect parameters RESELLER and CLIENT according to the required standard RESELLER UID and CLIENT UID on the system. If required (for example for cloud installations), you can remove the /CLIENT part of the URL.

```
redirect    location /CarrierPortal/login/RESELLER/CLIENT if root_req
redirect    location /CarrierPortal/mclogin/RESELLER/CLIENT if mini_req
```

Configure Backend Webserver and SOAP

The list of the backend web application servers and SOAP servers must be configured.

The alias names configured in /etc/hosts will work fine, however make sure you have all of the servers configured.

Here is the backend configuration for two webserver for the portal:

```
backend jtel_portal
...
server      jboss1 acd-jb1:8080 weight 1 cookie jboss1 check inter 1m
server      jboss2 acd-jb2:8080 weight 1 cookie jboss2 check inter 1m
```

And here is the backend configuration for two webserver for the portal:

```
backend jtel_soap
...
server      jboss1 acd-jb1:8080 weight 1 cookie jboss1 check inter 1m
server      jboss2 acd-jb2:8080 weight 1 cookie jboss2 check inter 1m
```

Optional Changes

User for haproxy Administration

The following URL can be used, to access the administration web admin site for the load balancer:

`http(s)://acd-store:7777`

This page can be used for example to deactivate certain resources for maintenance purposes.

Users, who can access the web admin site, must be configured in the configuration file.

First of all, a password must be generated, using the following command:

CAUTION PASSWORD

```
python2 -c 'import crypt; print crypt.crypt("<password>", "$5$jhaProxy")'
```

This command creates a password hash with a salt value *jhaProxy*. This hash and the user name is added to the configuration file. The line for newuser is added, and the user is added at the end of the group admin line:

```
userlist stats-auth
...
user  newuser  password <hashvalue>
group admin   users admin,jtel,newuser
```

Start the haproxy Service

Start the haproxy service as follows:

```
systemctl start haproxy.service
```

Test

Open the following URL in a browser:

<http://acd-lb/admin>

You should see the login screen of the jtel portal web application:

