# **Supervisor Grid Settings**

The Supervisor Grid provides a way to display some items in a grid layout.

See the **Supported Browsers** page at "Grid" for a list of compatible browsers.

The first time you call the Supervisor Grid, the layout is blank. By clicking Layout 1, Layout 2 and Layout 3, you can choose a layout. The settings are

The settings themselves can be made either in the Users - User master data (current user) or for each user in the "Settings" tab, then simply filter by "Grid". You can completely customise the layout. It is also possible to create the layout from scratch. Only the settings have to be entered.

#### Authorization

This feature requires the permission portal.Acd.AcdSupervisor.Grid

#### **Layout Principle**

The elements are arranged in a grid.

The width corresponds to 100% of the page width, and can be divided into a number of columns.

The height of the grid corresponds to a number of lines with a certain height. If you specify more lines than fit on the page, a scroll bar is rendered. The following settings can be made:

Setting	Example	Description
AcdSupervisor.Grid.Columns	10	Number of logical columns.
AcdSupervisor.Grid.Rows	20	Number of logical lines.
AcdSupervisor.Grid.RowHeight	41px	The line height. Valid units can be found in the CSS specification, for example, px or em.
		Note: % currently does not work. This is due to the early stadium of the grid layout in CSS.

#### Elements

The following elements can be inserted:

Element Names	Content
AgentsActive	Table "Active Agents".
AgentsAll	Table "All Agents"
CockpitVariables	Wallboard "Cockpit Variables".
CurrentCalls	Table "Current Calls".
DiallerCampaigns	Tabelle "Dialler Campaigns".
HelpRequests	Table "Help Requests".

Table "Inbound Mailboxes".
Table "Inbound Media Events".
Table "Media Events".
Table "Media History".
Table "Agents" and "Skills" from the real-time statistics.
Table from the "Inbound Real-Time" tab.
Table "Skills" from the daily statistics.
Table "Skills" from "Daily Statistics 15 Minuten".
Table "Skills" from "Daily Statistics 60 Minuten".
Table "Daily statistics".
Table "Daily statistics 15 minutes".
Table "Daily statistics 60 minutes".
The wallboard, area "Total".
The wallboard, area "Dialler Campaigns".
The wallboard, area "Group".

## **Elements Indication**

The elements are easily set with the setting AcdSupervisor.Grid.1, AcdSupervisor.Grid.2 and continuously defined. The numbers must be continuous, if there is a gap, no further elements are drawn.

The following syntax is used to specify the element:

ElementName, X, Y, Width, Height, Scaling

The following table is helpful when specifying the X / Y coordinate. The zero point is left above.

X=1, Y=1	X=2, Y=1	X=3, Y=1
X=1, Y=2	X=2, Y=2	X=3, Y=2
X=1, Y=3	X=2, Y=3	X=3, Y=3

#### **ElementName**

Name of the item from the list of items.

Χ

Specify the X coordinate in the virtual grid where the element is to be drawn.

Υ

Specify the Y coordinate in the virtual grid where the element is to be drawn.

## Width

The width of the element, as the number of virtual columns.

## Height

The height of the element, as the number of virtual rows.

# Scaling

The scaling of the element, as floating-point number with point (no comma use!).

For example, if you specify 0.1, the element is drawn in a tenth of its normal size.

If you specify 5, the element is drawn five times as large.

## Example

The following layout is the screenshot below.

Setting	Value
AcdSupervisor.Grid.1	WallboardAll,1,1,1,20,0.42
AcdSupervisor.Grid.2	WallboardGroups,9,1,2,20,0.42
AcdSupervisor.Grid.3	AgentsAll,2,1,7,8,0.75
AcdSupervisor.Grid.4	AgentsActive,2,9,7,8,0.75
AcdSupervisor.Grid.5	CurrentCalls,2,17,7,4,0.75
AcdSupervisor.Grid.Columns	10
AcdSupervisor.Grid.RowHeight	41px
AcdSupervisor.Grid.Rows	20

