

# Value Reference - CONNRES

## Purpose

The purpose of CONNRES is to provide a quick result regarding the end of a call.

Note, when referring to destination, this can mean:

- An agent called by the ACD
- An external destination called by the ACD
- A destination specified in a connect object in the IVR
- An agent called from the dialler
- A destination called from the dialler

In short, any destination called by the system whether as a result of an inbound call, or an outbound call (dialler or click to dial).

## Values

The following values are defined:

CONNRES	Meaning Inbound Calls	Meaning Outbound
0	<b>Caller Hangup</b>  The caller hung up the telephone, before the call to the destination was initiated.	<b>Outbound to number not used</b>  The initiator (usually the agent) hung up the telephone, before the call to the destination was actually initiated.
1	<b>OK</b>  Successful call to the destination.	<b>OK</b>  Successful outbound call to destination.
2	<b>No answer</b>  The destination did not answer the telephone.	<b>Number no answer</b>  The called destination did not answer.
3	<b>Busy</b>  The called destination was busy.	<b>Number busy</b>  The called destination was busy.
4	<b>Caller hangup</b>  The caller hungup whilst the call to the destination was being made.	<b>System aborted dial</b>  The outdial was aborted.
5	<b>ISDN cause</b>  A reason other than busy was received from the called destination.	<b>ISDN cause</b>  A reason other than busy was received from the called destination.
6	<b>Destination hangup</b>  The destination hungup during the whisper prompt before caller and destination were connected.	<b>Called party hangup before agent connected</b>  The called destination hungup after answering but before the connection to the agent was made. This can be during a whisper announcement if one was configured.

7	<b>Error</b> An error occurred when calling the destination.	<b>Error</b> An error occurred when calling the destination.
8	<b>OK, DTMF Hangup</b> Legacy, no longer supported.	<b>Not used</b>
9	<b>OK, DTMF Disconnect</b> Legacy, no longer supported.	<b>Not used</b>
10	<b>OK, Client Signal</b> Legacy, no longer supported.	<b>Not used</b>
11	<b>Voice Mail</b> Legacy, no longer supported.	<b>Not used</b>
12	<b>Number Blocked</b> The destination number was blocked in the restricted numbers table. The call was not made.	<b>Number Blocked</b> The destination number was blocked in the restricted numbers table. The call was not made.
13	<b>Agent to Agent Transfer</b> Legacy, no longer supported.	<b>Not used</b>
14	<b>Agent to External Transfer</b> Legacy, no longer supported.	<b>Not used</b>